

Vertiv™ Environet™ Alert

Release Notes

VERSION 1.4.2.1, MAY 2023

Release Notes Section Outline

1. Features and Bug Fixes
2. Supported Software Information
3. Technical Support Information

1. Features and Bug Fixes

This version of Vertiv™ Environet™ Alert focuses on minor feature enhancements, bug fixes, and platform updates. For simplicity and clarity, not all minor tasks (with reference numbers) are included in these release notes.

Version 1.4.2.1 Features

REFERENCE NUMBER	DESCRIPTION
US456	Updated JRE
US763	Updated Apache Web Server (includes remediation for vulnerability CVE-2022-42889)
US781	Updated Niagara

Version 1.4.2.1 Bug Fixes

REFERENCE NUMBER	DESCRIPTION
DE681	Clearing all records for selected sources fails when a new message is created
DE688	Copying a BACnet device leads to a device in Fault state with the value 0 on points
DE689	Improved BACnet device poll time
DE692	Improved points CSV export
DE693	Point CSV import missing column fix
DE702	Triggering a warning/alarm on a point associated to a circuit does not propagate the status to the circuit
DE703	Users page does not display after deleting prototypes
DE704	Cannot associate multiple circuits to the same rack feed
DE713	Creating two different floorplans with 200+ items in two separate boards locks the API GET requests
DE716	Importing a Points CSV file does not update the points
DE717	The Propagate Fault column is missing from the points CSV export file
DE718	Exporting a report as XLS that has more than 65,536 rows leads to an error
DE722	Clicking on add circuit does not do anything
DE724	Corrected ability to add device using SNMPv3 protocol
DE725	Clicking on a point in a list does not open the flyout if it was open before
DE728	Scheduled exports use XLS instead of XLSX
DE731	Points are missing from SNMPv1 import
DE732	SNMP devices are not getting polled after adding

2. Supported Software Information

- Client Browser (latest tested versions):
 - Microsoft Edge (103.0.1264.77)
 - Firefox (103.0.1)
 - Chrome (104.0.5112.81)
- Server Operating System:
 - Windows Server 2022 (Recommended)
 - Windows Server 2016, 2019
 - Windows 10 64-bit

3. Technical Support Information

For technical support, please email dcimsupport@vertiv.com, or call 1-800-222-5877 and select option 7.