

Vertiv™ Environet™ Alert

Release Notes

VERSION 1.4.3.1, DECEMBER 2023

Release Notes Section Outline

1. Features and Bug Fixes
2. Supported Software Information
3. Technical Support Information

1. Features and Bug Fixes

This version of Vertiv™ Environet™ Alert focuses on minor feature enhancements, bug fixes, performance improvements and platform updates. For simplicity and clarity, not all minor tasks (with reference numbers) are included in these release notes.

Version 1.4.3.1 Features

REFERENCE NUMBER	DESCRIPTION
US516	Reporting on alarms, timestamps in the server's time zone.
US518	[BACnet Routing] Exposed the BACnet router table.
US766	[BACnet Routing] Added route.
US767	[BACnet Routing] Allowed non-IP addressing for BACnet devices.
US768	[BACnet Routing] Discovery action.
US779	Updated Tomcat (9.0.73) and Apache Web (2.4.57).
US780	Updated Hazelcast (4.2.7).
US785	Added performance improvements.
US786	Added Modbus devices with the same IP address and different ports.
US796	Triggering a warning/alarm on a point associated to a circuit doesn't propagate the status to the circuit.

Version 1.4.3.1 Bug Fixes

REFERENCE NUMBER	DESCRIPTION
DE733	SNMP – The device last polled does not reflect the poll frequency setting.
DE734	Restoring some backups causes the system to hang.
DE743	Adding a circuit to the Rack Feed causes the circuit of the device to set all inputs to derived.
DE746	Attempting to log in using LDAP causes an error.
DE747	The tenant total power usage doesn't update based on data from the circuits.
DE751	Control groups change the state of only one point from all in the group.
DE752	Adding a device using SNMPv3 fails with the template that works for v1 and v2c.
DE771	The XLSX archived reports cannot be downloaded.
DE775	A trend visualization error occurs.

2. Supported Software Information

- Client Browser (latest tested versions):
 - Microsoft Edge (119.0.2151.97)
 - Firefox (119.0.1)
 - Chrome (119.0.6045.200)
- Server Operating System:
 - Windows Server 2022 (Recommended)
 - Windows Server 2016, 2019
 - Windows 10 64-bit

3. Technical Support Information

For technical support, please email dcimsupport@vertiv.com, or call 1-800-222-5877 and select option 7.